# North American Soil Geochemical plandscapes Projection

#### Goals

- Establish baseline geochemistry & microbiology for North America
- Interpret data in light of natural and human factors
  - Geology & climate
  - Industrialization, urbanization & agriculture
- Data for use by environmental agencies and others – baseline risk assessment
- Establish archive of soil samples for future studies
- Identify areas for additional sampling

#### Timeline

- Initiated by US, Canadian and Mexican, ed Geological Surveys – 2001
- Additional planning with EPA, other government agencies, universities
- Pilot Studies 2004
- Sampling started 2007
- ▶ 10+ years for completion

## **Previous Studies**

- Highways
- Shallow depth (20 cm)
- Native vegetation





Fig. 1. Location of 1323 soil samples collected by USGS from mid 1960s to late 1970s (Shacklette and Boerngen, 1984).


#### **Previous Studies**

- Natural
   Resources
   Conservation
   Service (1993) –
   metals in
   agricultural soils
- State surveys different methods




#### **GRTS**

- General Randomized Tessellation Stratified sampling design
- Ensures spatial uniformity and randomness unlike previous studies
- ▶ 13,596 sites for North America
- Over 4 times as many sites as Shacklette studies




# Canada





# Mexico






#### Site Selection

- ▶ 1 km² area centered on GRTS coordinate
- Select site "most-representative" of soil and landscape characteristics
- Avoid sites
  - <200m from major highways</p>
  - <50m from rural roads</p>
  - <100 m from buildings</p>
  - End rows of agricultural fields
  - Major industrial emitters power plants, smelters

## Site Selection



#### **Sample Analysis**


- Near-total extraction for ~44 major and trace elements (ICP-MS/ICP-AES/AA)
  - Pb, As, Hg, Se
- Total carbon, carbonate carbon (organice carbon by difference)
- Bacillus anthracis (anthrax) and other soil pathogens (EPA funding)
- Quantitative mineralogy by X-ray diffraction
- Phospholipid fatty acid (PLFA) analysis on 10% of samples



# Microbiology

- Phospholipid fatty acids (PLFA)
  - Can be used to identify microbial/bacterial communities
  - indicator of environmental impact & stress pollution, metals, temperature
- Soil Pathogens (Anthrax)
  - Determine areas of elevated risk to humans, in livestock and wildlife

#### Samples collected from each site




- 1: 0 to 5 cm depth regardless of horizon
  (1 2 kg + 1 fifty ml
  tube for soil
  pathogens)
- 2: A horizon (2 kg)
- 3: C horizon or closest approximation (1 2 kg)





#### Additional samples from every tenth site



- 1: 0 to 5 cm depth (1 centrifuge tube for PLFA analysis)
- 2: A horizon (1 centrifuge tube for PLFA analysis)
- 3: C horizon or closest approximation (1 centrifuge tube for PLFA analysis)
- \*Must be kept cold from time of collection.
- 4: Soil density from A & C horizons







Fig. 3. Location of soil sampling sites along the two transects across Canada and the US.

















# Pennsylvania



#### References

 http://minerals.cr.usgs.gov/projects/geoche mical\_landscapes/index.html

Applied Geochemistry 24 (2009)